Silicon Labs Timing USBXpress Driver README

Last updated March 3, 2018

CBPro supported evaluation boards and field programmer require a USBXpress driver.

The CBPro installer automatically installs this driver.

The driver installers are copied here for manual installation/debug. In general, this should not be required unless instructed to by a Silicon Labs support engineer.

There are two versions of the USBXpress driver:

Version 3.3

- 1) In folder USBXpress-Driver-v3.3
- 2) All versions of CBPro before 2.19.20 installed this
- 3) It works on Windows XP through Windows 10, except when:
 - a) Windows 10 Build 1607 or higher
 - b) UEFI instead of BIOS
 - c) Secure Boot turned on
- 4) CBPro installer 2.19.20 and higher installs this driver EXCEPT ON PCs WITH SECURE BOOT. The installer checks the registry to determine if the PC is using secure boot
- 5) The driver is "self signed" and has a valid digital signature
- 6) There are two sub-folders for variations of this driver:
 - a) Quiet-Mode: the CBPro installer runs this version to avoid dialog boxes on every CBPro update.
 - b) Verbose-Mode: this shows driver installer dialog boxes and is helpful when debugging driver issues.

Version 6.7.2.1

- 1) In folder USBXpress-Driver-v6.x
- 2) CBPro 2.19.20 and higher will install this on Windows 10 PCs that use secure boot
- 3) The driver is certified and signed by Microsoft
- 4) The CBPro installer passes /q option to USBXpressInstaller_*.exe to run in quiet mode, suppressing driver installation dialog boxes
- 5) If you double click USBXpressInstaller_*.exe from Windows Explorer, the driver installer will launch in verbose mode, showing standard dialog boxes.

Having Trouble Detecting an EVB?

Please try the following:

- 1) Reboot your PC
- 2) Launch CBPro and see if it detects EVB
- 3) If not, try installing or re-installing latest CBPro from http://www.silabs.com/cbpro (or newer Beta as appropriate)
- 4) Disconnect, wait a few seconds, and reconnect EVB
- 5) Launch CBPro and see if it detects EVB

- 6) If it does not detect the EVB, contact Silicon Labs via http://www.silabs.com/contactsupport.
 - a) Please attach the log.txt file that is found in C:\Users\YOURLOGIN\AppData\Local\Silicon Laboratories\ClockBuilder Pro where YOURLOGIN is your Windows login ID, such as jsmith. The log file contains some debugging information about the USB driver, such as:

USBXpress Device 0:

USBXpress SerialNumber: si5380cevb0106_000019d186b2 USBXpress Description: Silicon Labs Si538x/4x EVB

USBXpress LinkName:

\\?\usb#vid_10c4&pid_8999#si5380cevb0106_000019d186b2#{3c5e1462-5695-4e18-

876b-f3f3d08aaf18}

USBXpress VendorID: 10c4 USBXpress ProductID: 8999

USBXpress: First Open; detecting driver to use


USBXpress: CPU Architecture: x86

USBXpress: Secure Boot: No USBXpress: Trying new driver

USBXpress: Fail; trying old driver

USBXpress: Success; old driver will be used; SI_Open took 4 msec

- b) Send us information from the device manager
 - i) Open Device Manager
 - ii) You'll usually see a device named "USB API" or something like "Silicon Labs Si538x/4x EVB"
 - iii) In either case, double click the EVB device, click the Driver tab, and send us a screen shot such as:



c) Please contact your I.T. department if you need assistance gathering this information